CALIPSO SCIENCE DATA READERS Release 3.3v1

Introduction

The Cloud-Aerosol Lidar and Infrared Pathfinder Satellite Observation (CALIPSO) satellite will provide new insight into the role that clouds and atmospheric aerosols play in regulating Earth's weather, climate and air quality. In order to do this, a wide variety of scientific data products will be available to the science community. These products will be derived from the data acquired from three on-board instruments; the Cloud-Aerosol Lidar with Orthogonal Polarization (CALIOP), the Wide Field Camera (WFC) and the Imaging Infrared Radiometer (IIR). These data products are described in the CALIPSO Data Products Catalog (DPC) currently available on the CALIPSO public web site at URL:

http://www-calipso.larc.nasa.gov/resources/project_documentation.php. The Langley Research Center (LaRC) Atmospheric Science Data Center (ASDC) processes, archives, and disseminates the CALIPSO data products. The web site address for the ASDC is: https://eosweb.larc.nasa.gov/HBDOCS/hdf_data_manipulation.html. These data products are output using the Hierarchical Data Format (HDF). More information concerning HDF formats can be found on the National Center for Supercomputing Applications web site at: http://www.ncsa.illinois.edu/UserInfo/Resources/Hardware/News/copper/ByName/HDF_Library.html.

Readers

A set of basic CALIPSO data product readers has been developed to aid users in their ability to read the HDF formatted files. This set of readers is written using the Interactive Data Language (IDL) available through EXELIS Visual Information Solutions at URL: http://www.exelisvis.com and go hand in hand with either the CALIPSO Data Products Catalog (DPC) Release 3.6. A list of the major data products, their associated readers, commons, check programs, and the corresponding DPC Table numbers are contained in the tables below.

Due to the nature of the HDF formatting and the need to assign each parameter to the appropriately named variable, there must be an exact match between variable names stored in the file and the command parameter used to retrieve that variable. These readers are written to provide users with the greatest flexibility to select only those parameters that are necessary for their applications. They were not written for efficiency as much as simplicity. There is a one-line call for each parameter, that can be commented out by placing a ';' at the beginning of the line. Already commented out in each program, but left available for the users, are print statements that will provide more detailed information about each parameter contained in the HDF file. Each reader takes as input two quoted string parameters, PATH and FILE NAME. The PATH name contains the directory path to the folder that contains the data, and the FILE NAME contains the full name of the file to be read.

The commons associated with each data product reader contain abbreviated names for each parameter. If the user chooses not to read every data product, these variables will not be filled, but will not present any problems if left in the common. Of course, the user may change these names to match the desired names for their application, but care should be taken to ensure that names are changed in the IDL code as well as the associated common. In some cases, single dimension arrays are read as two dimensional with the initial dimension being set to 1. This does not affect the data in any way, but may need to be considered later when working with the arrays. In order to correct this issue, a simple call to the IDL REFORM function will adjust the array to a single dimension. For example, ArrayA is created with dimensions of (1,50). Issuing the command ArrayA = REFORM(ArrayA, /OVERWRITE) returns ArrayA with a single dimension of (50), and the actual data remains unchanged.

Last Updated: August 9, 2013

Simple check programs are also provided for each of the readers. These check programs are called at the end of each reader program, and are a double check to ensure that all variables are filled. The calls to the check programs can be commented out once the user is certain that all parameters of interest are read correctly. The check programs issue a 'HELP, Variable' for each of the common variables. The HELP command provides common, format, dimension and static value information for all variables. The output from the HELP command is sent to STDOUT, unless otherwise redirected. For a more detailed description of data formats, units, and ranges, please refer to the CALIPSO DPC.

Major Data Products, Associated Readers, Commons, Check Programs, Corresponding DPC Table Numbers

| DATA PRODUCT | READER NAME (.pro) | COMMON NAME (.pro) | CHECKIT NAME (.pro) | DPC Version 3.6 |
|---|-----------------------|---------------------|------------------------|------------------|
| | | | | TABLE NUMBERS |
| Lidar Level 1 | read_hdf_l1 | L1_COMMON | Checkit_L1 | 7, 8, 9, 10 |
| Lidar Level 2 1/3km Cloud Column and Layer | read_hdf_l2_cl33 | L2_CL33_COMMON | Checkit_CL33 | 26, 27, 28 |
| Lidar Level 2 1km Cloud Column and Layer | read_hdf_l2_cl01 | L2_CL01_COMMON | Checkit_CL01 | 26, 29, 30 |
| Lidar Level 2 5km Cloud Column and Layer | read_hdf_l2_cl05 | L2_CL05_COMMON | Checkit_CL05 | 26, 31, 32 |
| Lidar Level 2 5km Aerosol Column and Layer | read_hdf_l2_al05 | L2_AL05_COMMON | Checkit_AL05 | 26, 33, 34 |
| Lidar Level 2 Aerosol Profile, Best Estimate | read_hdf_l2_aerprf | L2_AERPRF_COMMON | Checkit_AERPRF | 36, 37 |
| Lidar Level 2 Cloud Profile | read_hdf_l2_cldprf | L2_CLDPRF_COMMON | Checkit_CLDPRF | 39, 40 |
| Lidar Level 2 Vertical Feature Mask | read_hdf_l2_vfm | L2_VFM_COMMON | Checkit_VFM | 42, 43 |
| Lidar Level 2 Polar Stratospheric Cloud Mask | read_hdf_l2_psc | L2_PSC_COMMON | Checkit_PSC | 46, 47 |
| WFC 1km Registered Science Record | read_hdf_wfc_1rs | WFC_1RS_COMMON | Checkit_W1RS | 18, 19 |
| WFC 1km Native Science Record | read_hdf_wfc_1ns | WFC_1NS_COMMON | Checkit_W1NS | 18, 20 |
| WFC 125m Native Science Record | read_hdf_wfc_125 | WFC_125_COMMON | Checkit_W125 | 18, 21 |
| IIR Level 2 Swath Science Record | read_hdf_iir_l2_swath | IIR_L2_SWATH_COMMON | Checkit_IIR_SWATH | 52, 53 |
| IIR Level 2 Track Science Record | read_hdf_iir_l2_track | IIR_L2_TRACK_COMMON | Checkit_IIR_TRACK | 49, 50 |
| Lidar Level 1.5 Expedited Data | read_hdf_l15 | L15_COMMON | Checkit_L15 | 68, 69, 70 |
| Lidar Level 3 Aerosol Profile | read_hdf_13 | L3_COMMON | Checkit_L3 | 55 - 64 |
| IIR Level 1 Science Record | read_hdf_iir_l1 | IIR_L1_COMMON | Checkit IIR | 12, 13, 14 |

These readers can be called from within a program, or embedded into the user's program. Remember to include the associated common into the application software in order to have full access to the data. The user is also reminded to make certain that the IDL path parameters are set correctly under the IDL Preferences options.

Last Updated: August 9, 2013

To run these programs from the **Windows** IDL Development Environment (IDLDE) simply enter the command:

<Reader Name>, <Data Directory Full Path (single quotes)>, <Data File Name (single quotes)>

Examples in Windows Environment:

```
read hdf 11, 'C:\DATA\', 'L1-2007-00-00T00-00-00ZN.hdf'
read hdf 12 cl33, 'C:\DATA\', 'L2 2007-00-00T00-00-00ZN 333mCloudLayer.hdf'
read hdf 12 cl01, 'C:\DATA\', 'L2 2007-00-00T00-00-00ZN 1kmCloudLayer.hdf'
read hdf 12 cl05, 'C:\DATA\', 'L2 2007-00-00T00-00-00ZN 5kmCloudLayer.hdf'
read hdf 12 al05, 'C:\DATA\', 'L2 2007-00-00T00-00-00ZN 5km aer layer.hdf'
read hdf 12 aerprf, 'C:\DATA\', 'L2 2007-00-00T00-00-00ZN 5kmAerosolProfile.hdf'
read hdf 12 aerfxd, 'C:\DATA\', 'L2 2007-00-00T00-00-00ZN 40kmAerosolProfile.hdf'
read hdf 12 cldprf, 'C:\DATA\', 'L2 2007-00-00T00-00-00ZN 5km CloudProfile.hdf'
read hdf 12 vfm, 'C:\DATA\', 'L2 2007-00-00T00-00-00ZN VFM.hdf'
read hdf 12 psc, 'C:\DATA\', 'L2 2007-00-00T00-00-00ZN PSC.hdf'
read hdf wfc 125, 'C:\DATA\', 'WFC125mz01.01d000000-000000.hdf'
read hdf wfc 1ns, 'C:\DATA\', 'WFC1Kmz01.01d000000-000000.hdf'
read hdf wfc 1rs, 'C:\DATA\', 'WFCIIRz01.01d000000-000000.hdf'
read hdf iir 11, 'C:\DATA\', 'CAL IIR L1-Prov-V1-11.2007-00-00T00-00-00ZD.hdf'
read hdf iir 12 swath, 'C:\DATA\', 'CAL IIR L2 Swath-Beta-V2-02.2007-00-00T00-00-00ZN.hdf'
read hdf iir 12 track, 'C:\DATA\', 'CAL IIR L2 Track-Beta-V2-02.2007-00-00T00-00-00ZN.hdf'
read hdf 115, 'C:\DATA\',' CAL LID L15 Exp-Beta-V3-02.2011-05-24T21-00-00ZD.hdf'
read hdf 13,'C:\DATA\',' CAL LID L3 APro AllSky-Beta-V1-00.2011-05D.hdf'
```

To run these programs from the **Unix** IDL Development Environment (IDLDE) simply enter the command:

<Reader Name>, <Data Directory Full Path (single quotes)>, <Data File Name (single quotes)>

Examples in Unix Environment:

```
read hdf 11, '/DATA', 'L1-2007-00-00T00-00-00ZN.hdf'
read hdf 12 cl33, '/DATA', 'L2 2007-00-00T00-00-00ZN 333mCloudLayer.hdf'
read hdf 12 cl01, '/DATA', 'L2 2007-00-00T00-00-00ZN 1kmCloudLayer.hdf'
read hdf 12 cl05, '/DATA', 'L2 2007-00-00T00-00-00ZN 5kmCloudLayer.hdf'
read hdf 12 al05, '/DATA', 'L2 2007-00-00T00-00-00ZN 5km aer layer.hdf'
read hdf 12 aerprf, '/DATA', 'L2 2007-00-00T00-00-00ZN 5kmAerosolProfile.hdf'
read hdf 12 aerfxd, '/DATA', 'L2 2007-00-00T00-00-00ZN 40kmAerosolProfile.hdf'
read hdf 12 cldprf, '/DATA', 'L2 2007-00-00T00-00-00ZN 5km CloudProfile.hdf'
read hdf 12 vfm, '/DATA', 'L2 2007-00-00T00-00-00ZN VFM.hdf'
read hdf 12 psc, '/DATA', 'L2 2007-00-00T00-00-00ZN PSC.hdf'
read_hdf_wfc_125, '/DATA', 'WFC125mz01.01d000000-000000.hdf'
read hdf wfc 1ns, '/DATA', 'WFC1Kmz01.01d000000-000000.hdf'
read hdf wfc 1rs, '/DATA', 'WFCIIRz01.01d000000-000000.hdf'
read hdf iir 11, '/DATA', 'CAL IIR L1-Prov-V1-11.2007-00-00T00-00-00ZD.hdf'
read hdf iir 12 swath, '/DATA/', 'CAL IIR L2 Swath-Beta-V2-02.2007-00-00T00-00-00ZN.hdf'
read hdf iir 12 track, '/DATA/', 'CAL IIR L2 Track-Beta-V2-02.2007-00-00T00-00-00ZN.hdf'
read hdf 115,'/DATA/',' CAL LID L15 Exp-Beta-V3-02.2011-05-24T00-00-00ZD.hdf'
read hdf 13,'/DATA/',' CAL LID L3 APro AllSky-Beta-V1-00.2011-05D.hdf'
```

Last Updated: August 9, 2013